FxCraft visual order editor

FxCraft visual order editor allows for easy and intuitive position management by dragging the entry, SL or TP level lines on the chart.

After applying it to the chart, it draws horizontal lines, which you can move to easily and intuitively modify your orders - you only need to choose a line, for instance a stop loss and drag it to the desired level - it's fast, intuitive and graphical.

In the same way it is possible to modify take profit and pending orders entry levels.

Additional functionality is a break even line - after setting it, when the price crosses it, your order will be secured - stop loss will be moved so as to assure that there will be no loss in case of a market reversal. Break even functionality is activated by setting use_be to true and setting default BE level.

Next interesting feature is a cancel level line. After setting it, when the price crosses it, pending order will be cancelled. It allows to obtain the functionality similiar to an "one cancels another" order. Cancel level functionality is activated by setting use_cl to true and setting the default cancel level.

Configuration:

The variables responsible for the operation of the EA:

use_timer	Specifies whether to operate in an asynchronous mode.
	Asynchronous mode (true): EA checks every second if any of the orders were edited.
	Synchronous mode (false): checking is done when the tick comes.
	Please note: when use_timer is set to true, editing of the EA settings is not possible - you need to remove it and apply to the chart again.
delete_on_deinit	When it is set to true, once EA is removed, all lines that derive from it are removed from the chart.

Stop Loss

default_sl_level	Size of a default stop loss. When it is set to zero and the stop loss level has not been set for the order, the line will not be drawn.
default_trailing_stop	Size of default trailing stop.
sl_color	stop loss line colour
sl_style	stop loss line style

By moving the "fvoe_sl_ ..." line, you can modify stop loss price level of a selected order.

To activate trailing stop, select the "fvoe_sl_ ..." line for the order for which you want to "pull" stop loss, right click the mouse and choose "Horizontal Line - properties".

In the description pane, you will find the entry:

#1234567 stop loss

To set trailing stop for this order to 20 pips, just type **ts=20** at the, so that the whole formula is:

#1234567 stop loss ts=20

Please note:

- The number cannot be followed by any character.
- Similarly, do not enter a space before or after the = character.=.
- Editing an order by moving the line at a distance further than TS will not take any effect: EA will restore the distance resulting from the TS setting.
- To remove trailing stop, just edit the description and remove the said **ts=20** string.

Take Profit

	Size of a default take profit. When it is set to zero and the take profit level has not been set for the order, the line will not be drawn
tp_color	Take profit line colour
tp_style	Take profit line style

By moving the "fvoe tp ..." line, you can modify the take profit price level of a selected order.

Break Even

use_be	Specifies whether to activate the break even function.
default_be_level	Default break even level.
be_offset	Break even shift.
be_color	Break even line colour.
be_style	Break even line style.

The break even functionality is activated by setting use_be to true and specifying a default level of default_be_level. By moving the "fvoe_be_ ..." line, you can modify the break even price level of an order. If the line is set and it is exceeded by the price, the order will be secured - stop loss will be shifted so that the position does not bring any losses in case of return (EA sets stop loss at the be_offset distance from the opening price of the order).

Cancel Level

use_cl	Specifies whether to activate the cancel level function.
default_cl_level	Default cancel level.
cl_color	Cancel level line colour.
cl_style	Cancel level line style.

The cancel level functionality is activated by setting use_cl and specifying a default cancel level. If the "fvoe_cl_ ..." line is set and it gets exceeded by the price, the pending order will be cancelled.

Close Part

use_cp	Specifies whether to activate the close part function.
cp_size_or_percent	If true: enter in cp_lots the number of lots which EA will close at the next levels designated by cp_levels. If false: enter in cp_lots the percentage of lots which will be cumulatively closed at the next cp_level.
cp_levels	Consecutive default closing levels of some positions are calculated in pips from the position opening level.
cp_lots	The number (or percentage) of position lots which should be closed.
cp_color	Close part line colour.
cp_style	Close part line style.

By moving the "fvoe_cp_ ..." line, you can modify the level which results in closing of the positions designated by cp_lots when it is exceeded. cp_lots.

Below you can find example scenarios of the default settings for the close part function:

Example 1.

We are opening a position for 10 lots with the set parameters:

```
cp_size_or_percent = true;
cp_levels = 20,30,40;
cp_lots = 3,2,100;
```

After making the profit of 20 pips, EA will close 3 lots and determine the level of the next closing at 10 pips (i.e. 30 from the opening of the position). After making the profit of 30 pips, the next 2 lots will be closed and the closing level will again go 10 pips further. The last of the six lots will be closed at the level of 40 pips from the opening price.

Example 2.

We are opening a position for 10 lots with the set parameters:

```
cp_size_or_percent = false;
cp_levels = 5,10,15,40,60,70,90;
cp_lots = 12.5,25,50,90;
```

After making the profit of 5 pips, EA will close 1.25 lots and determine the level of the next closing at 5 pips (i.e. 10 from the opening of the position). After making the profit of 10 pips, the next 1.25 lots will be closed (i.e. 2.5 in total) and the closing level will again go 5 pips further. At the level of 15 pips from the opening of the position, 2.5 lots will be closed (i.e. 50% from the beginning in total), while after exceeding the level of 40 pips, only 10% of the initial position will be left. Further closing levels are ignored since there are only four numbers in the cp_lots variable.

Please note

- The parameters cp_lots and cp_levels cannot contain any spaces or other characters between the numbers, but only "," (comma) as a separator..


Open Level

showOLforOpenOrders	Shows open level line also for open orders	
ol_sell_color	SELL pending orders line colour	
ol_sell_style	SELL pending orders line style	
ol_buy_color	BUY pending orders line colour	
ol_buy_style	BUY pending orders line style	

By moving the "fvoe_ol_ ..." line, you can modify the opening price of a selected pending order.

Possible values of the "..._ style "parameter responsible for line style:

0	STYLE_SOLID
1	STYLE_DASH
2	STYLE_DOT
3	STYLE_DASHDOT
4	STYLE_DASHDOTDOT



Possible further modifications on request.

Examples of add-ons:

- trailing stop in sync with indicators (eg Bbands Stops).
- several FVOE on the same pairs on different charts.
- Trailing stop after BE